

Prerequisites:


To access to a remote computer at FIU you must first connect to the FIU VPN.

Here is a link to download an instructional manual for setting up FIU's VPN:

<http://web.eng.fiu.edu/tech/VPN/>


You will also need the IP Address/hostname of the computer you remoting to:

To do this open command prompt on the computer by searching for **cmd** in windows search.



To get your **IP address** use the command **ipconfig** on Command Prompt: Under **IPv4 Address**

Then to get your hostname use **nslookup <Your.IP.Address.Here>**: Under **Name:**



```
Administrator: Command Prompt
Microsoft Windows [Version 10.0.14393]
(c) 2016 Microsoft Corporation. All rights reserved.

C:\Windows\system32>ipconfig

Windows IP Configuration

Ethernet adapter Ethernet:

    Connection-specific DNS Suffix  . : 
    Link-local IPv6 Address . . . . . : 
    IPv4 Address. . . . . : Your IP Address
    Subnet Mask . . . . . : 
    Default Gateway . . . . . : 

Tunnel adapter isatap.fiu.edu:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . : fiu.edu

Tunnel adapter Teredo Tunneling Pseudo-Interface:


    Connection-specific DNS Suffix  . : 
    IPv6 Address. . . . . : 2001:0:34f1:8072:1811:dea:f599:2cb2
    Link-local IPv6 Address . . . . . : fe80::1811:dea:f599:2cb2%8
    Default Gateway . . . . . : ::

C:\Windows\system32>nslookup <Your.IP.Address.Here>
Server: 
Address: 
Name: Your Hostname
Address:
```


Enabling Remote Desktop (Windows 10)

To remote to desire computer, you must first enable it Windows 10 Settings:

In Windows 10 Search for **Remote Desktop Settings** and then click it.



Left click the switch under **Enable Remote Desktop**: A confirmation will pop up, hit **Confirm**



Here is a link for other ways to enable remote desktop through control panel:


Under “How to enable Remote Desktop on Windows 10 using Control Panel”

<https://pureinfotech.com/enable-remote-desktop-windows-10/>


Remoting to Desktop

Note: You MUST sign in to the FIU VPN first to access a remote desktop at FIU.

First Search for **Remote Desktop Connection**:




Enter your remote desktop IP address or Hostname in the **Computer:** Text box



After connecting to it will ask for the credentials for the Desktop you are remoting to.

You can use the **More choices** and choose **Use a different account**, to input your credentials if it does not let you change username.



This will pop up once credentials are correct just press **Yes**.

